



# Manage UNIX user configurations

## ONTAP 9.14.1 REST API reference

NetApp  
April 02, 2024

# Table of Contents

|   |    |
|---|----|
| Manage UNIX user configurations . . . . .                   | 1  |
| Name-services unix-users endpoint overview . . . . .        | 1  |
| Retrieve all UNIX users for all SVMs . . . . .              | 5  |
| Create a local UNIX user configuration for an SVM . . . . . | 11 |
| Delete a UNIX user configuration for an SVM . . . . .       | 17 |
| Retrieve UNIX user information for a user and SVM . . . . . | 19 |
| Update UNIX user information for a user and SVM . . . . .   | 24 |

# Manage UNIX user configurations

## Name-services unix-users endpoint overview

### Overview

You can use this API to display local UNIX user information and to control UNIX user configurations.

### Retrieving UNIX user information

You can use the UNIX user GET endpoint to retrieve all of the local UNIX user configurations for data SVMs.

### Examples

#### Retrieving all of the fields for UNIX user configurations for all SVMs

```
# The API:  
/api/name-services/unix-users  
  
# The call:  
curl -X GET "https://<mgmt-ip>/api/name-services/unix-users?fields=*" -H  
"accept: application/json"  
  
# The response:  
{  
  "records": [  
    {  
      "svm": {  
        "uuid": "25b363a6-2971-11eb-88e1-0050568eef4",  
        "name": "vs1"  
      },  
      "name": "string",  
      "id": 7,  
      "primary_gid": 0,  
      "full_name": "string"  
    },  
    {  
      "svm": {  
        "uuid": "3f479a01-2971-11eb-88e1-0050568eef4",  
        "name": "vs2"  
      },  
      "name": "nobody",  
      "id": 65535,  
      "primary_gid": 65535,  
    }  
  ]  
}
```

```
"full_name": "",  
},  
{  
    "svm": {  
        "uuid": "3f479a01-2971-11eb-88e1-0050568eefc4",  
        "name": "vs2"  
    },  
    "name": "pcuser",  
    "id": 65534,  
    "primary_gid": 65534,  
    "full_name": ""  
},  
{  
    "svm": {  
        "uuid": "3f479a01-2971-11eb-88e1-0050568eefc4",  
        "name": "vs2"  
    },  
    "name": "root",  
    "id": 0,  
    "primary_gid": 1,  
    "full_name": ""  
}  
],  
"num_records": 4  
}
```

---

## Retrieving the UNIX user configuration of a specific SVM

---

```

# The API:
/api/name-services/unix-users

# The call:
curl -X GET "https://<mgmt-ip>/api/name-services/unix-
users?svm.uuid=25b363a6-2971-11eb-88e1-0050568eef4&fields=*" -H "accept:
application/json"

# The response:
{
  "records": [
    {
      "svm": {
        "uuid": "25b363a6-2971-11eb-88e1-0050568eef4",
        "name": "vs1"
      },
      "name": "user1",
      "id": 1,
      "primary_gid": 1,
      "full_name": "Full User Name for user1"
    }
  ],
  "num_records": 1
}

```

---

## Retrieving a UNIX user configuration of a specific SVM and user

---

```

# The API:
/api/name-services/unix-users/{svm.uuid}/{name}

# The call:
curl -X GET "https://<mgmt-ip>/api/name-services/unix-users/25b363a6-2971-
11eb-88e1-0050568eef4/user1" -H "accept: application/json"

# The response:
{
  "svm": {
    "uuid": "25b363a6-2971-11eb-88e1-0050568eef4",
    "name": "vs1"
  },
  "name": "user1",
  "id": 1,
  "primary_gid": 1,
  "full_name": "Full User Name for user1"
}

```

## Creating a UNIX user configuration

The UNIX user POST endpoint creates a UNIX user configuration for the specified SVM.

### Examples

#### Creating a UNIX user configuration with all fields specified

```

# The API:
/api/name-services/unix-users

# The call:
curl -X POST "https://<mgmt-ip>/api/name-services/unix-users" -H "accept:
application/json" -d "{ \"full_name\": \"Full user name\", \"id\": 7,
\"name\": \"user2\", \"primary_gid\": 10, \"skip_name_validation\": false,
\"svm\": { \"name\": \"vs1\", \"uuid\": \"25b363a6-2971-11eb-88e1-
0050568eef4\" } }"

```

#### Creating a UNIX user configuration with only mandatory fields specified

```
# The API:  
/api/name-services/unix-users  
  
# The call:  
curl -X POST "https://<mgmt-ip>/api/name-services/unix-users" -H "accept: application/json" -d "{ \"id\": 8, \"name\": \"user9\", \"primary_gid\": 10, \"svm\": { \"name\": \"vs1\", \"uuid\": \"25b363a6-2971-11eb-88e1-0050568eefc4\" } }"
```

## Updating a UNIX user configuration

The UNIX user PATCH endpoint updates the UNIX user configuration for the specified user and SVM. The following example shows a PATCH operation:

```
# The API:  
/api/name-services/unix-users/{svm.uuid}/{name}  
  
# The call:  
curl -X PATCH "https://<mgmt-ip>/api/name-services/unix-users/25b363a6-2971-11eb-88e1-0050568eefc4/user1" -H "accept: application/json" -d "{ \"full_name\": \"Full name\", \"id\": 7, \"primary_gid\": 10 }"
```

## Deleting a UNIX user configuration

The UNIX user DELETE endpoint deletes the specified UNIX user for the specified SVM. The following example shows a DELETE operation:

```
# The API:  
/api/name-services/unix-users/{svm.uuid}/{name}  
  
# The call:  
curl -X DELETE "https://<mgmt-ip>/api/name-services/unix-users/25b363a6-2971-11eb-88e1-0050568eefc4/user1" -H "accept: application/json"
```

## Retrieve all UNIX users for all SVMs

GET /name-services/unix-users

**Introduced In:** 9.9

Retrieves all of the UNIX users for all of the SVMs.

## Important notes

- The current UNIX users count can be retrieved from the num\_records field by calling the API with the parameter "return\_records=false".

## Related ONTAP commands

- vserver services name-service unix-user show

## Parameters

| Name           | Type          | In    | Required | Description   |
|----------------|---------------|-------|----------|---|
| id             | integer       | query | False    | Filter by id  |
| name           | string        | query | False    | Filter by name  |
| primary_gid    | integer       | query | False    | Filter by primary_gid   |
| svm.uuid       | string        | query | False    | Filter by svm.uuid  |
| svm.name       | string        | query | False    | Filter by svm.name  |
| full_name      | string        | query | False    | Filter by full_name   |
| fields         | array[string] | query | False    | Specify the fields to return.   |
| max_records    | integer       | query | False    | Limit the number of records returned.   |
| return_records | boolean       | query | False    | <p>The default is true for GET calls. When set to false, only the number of records is returned.</p> <ul style="list-style-type: none"><li>Default value: 1</li></ul> |

| Name           | Type          | In    | Required | Description  |
|----------------|---------------|-------|----------|--|
| return_timeout | integer       | query | False    | <p>The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached.</p> <ul style="list-style-type: none"> <li>• Default value: 1</li> <li>• Max value: 120</li> <li>• Min value: 0</li> </ul> |
| order_by       | array[string] | query | False    | Order results by specified fields and optional [asc]   |

## Response

```
Status: 200, Ok
```

| Name        | Type                               | Description                  |
|-------------|------------------------------------|------------------------------|
| _links      | <a href="#">_links</a>             |                              |
| num_records | integer                            | Number of UNIX user records. |
| records     | array[ <a href="#">unix_user</a> ] |                              |

## Example response

```
{  
  "_links": {  
    "next": {  
      "href": "/api/resourcelink"  
    },  
    "self": {  
      "href": "/api/resourcelink"  
    }  
  },  
  "num_records": 1,  
  "records": {  
    "_links": {  
      "self": {  
        "href": "/api/resourcelink"  
      }  
    },  
    "full_name": "Full User Name for user1",  
    "name": "user1",  
    "svm": {  
      "_links": {  
        "self": {  
          "href": "/api/resourcelink"  
        }  
      },  
      "name": "svm1",  
      "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"  
    }  
  }  
}
```

## Error

Status: Default, Error

| Name  | Type           | Description |
|-------|----------------|-------------|
| error | returned_error |             |

## Example error

```
{  
  "error": {  
    "arguments": {  
      "code": "string",  
      "message": "string"  
    },  
    "code": "4",  
    "message": "entry doesn't exist",  
    "target": "uuid"  
  }  
}
```

## Definitions

## See Definitions

href

| Name | Type   | Description |
|------|--------|-------------|
| href | string |             |

\_links

| Name | Type | Description |
|------|------|-------------|
| next | href |             |
| self | href |             |

\_links

| Name | Type | Description |
|------|------|-------------|
| self | href |             |

svm

SVM, applies only to SVM-scoped objects.

| Name   | Type   | Description   |
|--------|--------|---|
| _links | _links |   |
| name   | string | The name of the SVM. This field cannot be specified in a PATCH method.              |
| uuid   | string | The unique identifier of the SVM. This field cannot be specified in a PATCH method. |

unix\_user

| Name      | Type    | Description                                       |
|-----------|---------|---|
| _links    | _links  |   |
| full_name | string  | User's full name.                                 |
| id        | integer | UNIX user ID of the specified user.               |
| name      | string  | UNIX user name to be added to the local database. |

| Name                 | Type                | Description   |
|----------------------|---------------------|---|
| primary_gid          | integer             | Primary group ID to which the user belongs.   |
| skip_name_validation | boolean             | Indicates whether or not the validation for the specified UNIX user name is disabled. |
| svm                  | <a href="#">svm</a> | SVM, applies only to SVM-scoped objects.  |

#### error\_arguments

| Name    | Type   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

#### returned\_error

| Name      | Type                                   | Description                                 |
|-----------|--|---|
| arguments | <a href="#">array[error_arguments]</a> | Message arguments                           |
| code      | string                                 | Error code                                  |
| message   | string                                 | Error message                               |
| target    | string                                 | The target parameter that caused the error. |

## Create a local UNIX user configuration for an SVM

POST /name-services/unix-users

**Introduced In:** 9.9

Creates the local UNIX user configuration for an SVM.

### Important notes

- The default limit for local UNIX users is 32768.

## Parameters

| Name           | Type    | In    | Required | Description   |
|----------------|---------|-------|----------|---|
| return_records | boolean | query | False    | <p>The default is false. If set to true, the records are returned.</p> <ul style="list-style-type: none"><li>• Default value:</li></ul> |

## Request Body

| Name                 | Type                   | Description   |
|----------------------|------------------------|---|
| _links               | <a href="#">_links</a> |   |
| full_name            | string                 | User's full name.   |
| id                   | integer                | UNIX user ID of the specified user.   |
| name                 | string                 | UNIX user name to be added to the local database.                                     |
| primary_gid          | integer                | Primary group ID to which the user belongs.   |
| skip_name_validation | boolean                | Indicates whether or not the validation for the specified UNIX user name is disabled. |
| svm                  | <a href="#">svm</a>    | SVM, applies only to SVM-scoped objects.  |

## Example request

```
{  
    "_links": {  
        "self": {  
            "href": "/api/resourcelink"  
        }  
    },  
    "full_name": "Full User Name for user1",  
    "name": "user1",  
    "svm": {  
        "_links": {  
            "self": {  
                "href": "/api/resourcelink"  
            }  
        },  
        "name": "svml",  
        "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"  
    }  
}
```

## Response

Status: 201, Created

| Name        | Type                               | Description                  |
|-------------|------------------------------------|------------------------------|
| _links      | <a href="#">_links</a>             |                              |
| num_records | integer                            | Number of UNIX user records. |
| records     | array[ <a href="#">unix_user</a> ] |                              |

## Example response

```
{  
    "_links": {  
        "next": {  
            "href": "/api/resourcelink"  
        },  
        "self": {  
            "href": "/api/resourcelink"  
        }  
    },  
    "num_records": 1,  
    "records": {  
        "_links": {  
            "self": {  
                "href": "/api/resourcelink"  
            }  
        },  
        "full_name": "Full User Name for user1",  
        "name": "user1",  
        "svm": {  
            "_links": {  
                "self": {  
                    "href": "/api/resourcelink"  
                }  
            },  
            "name": "svm1",  
            "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"  
        }  
    }  
}
```

## Headers

| Name     | Description                               | Type   |
|----------|---|--------|
| Location | Useful for tracking the resource location | string |

## Error

Status: Default

## ONTAP Error Response Codes

| Error Code | Description   |
|------------|---|
| 2621706    | The specified SVM UUID is incorrect for the specified SVM name  |
| 2621516    | This operation is only supported on a data SVM  |
| 23724066   | The specified UNIX user name is too long. Maximum supported length is 64 characters.  |
| 3277051    | The specified UNIX user name contains invalid characters. Valid characters are 0-9, A-Z, a-z, ".", "_" and "-".             |
| 23724128   | The specified UNIX user full-name contains the invalid character ':'.   |
| 23724089   | The specified UNIX user full-name is too long. Maximum supported length is 256 characters.                                  |
| 23724055   | Internal error. Failed to create the UNIX user for the SVM. Verify that the cluster is healthy, then try the command again. |
| 23724090   | Configuring individual entries is not supported because file-only configuration is enabled.                                 |
| 3277025    | Failed to create the UNIX user for the SVM because the system limit has been reached.                                       |

| Name  | Type           | Description |
|-------|----------------|-------------|
| error | returned_error |             |

### Example error

```
{
  "error": {
    "arguments": {
      "code": "string",
      "message": "string"
    },
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

## Definitions

## See Definitions

href

| Name | Type   | Description |
|------|--------|-------------|
| href | string |             |

\_links

| Name | Type | Description |
|------|------|-------------|
| self | href |             |

svm

SVM, applies only to SVM-scoped objects.

| Name   | Type   | Description   |
|--------|--------|---|
| _links | _links |   |
| name   | string | The name of the SVM. This field cannot be specified in a PATCH method.              |
| uuid   | string | The unique identifier of the SVM. This field cannot be specified in a PATCH method. |

unix\_user

| Name                 | Type    | Description   |
|----------------------|---------|---|
| _links               | _links  |   |
| full_name            | string  | User's full name.   |
| id                   | integer | UNIX user ID of the specified user.   |
| name                 | string  | UNIX user name to be added to the local database.                                     |
| primary_gid          | integer | Primary group ID to which the user belongs.   |
| skip_name_validation | boolean | Indicates whether or not the validation for the specified UNIX user name is disabled. |

| Name | Type | Description                              |
|------|------|--|
| svm  | svm  | SVM, applies only to SVM-scoped objects. |

\_links

| Name | Type | Description |
|------|------|-------------|
| next | href |             |
| self | href |             |

error\_arguments

| Name    | Type   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

returned\_error

| Name      | Type                   | Description                                 |
|-----------|------------------------|---|
| arguments | array[error_arguments] | Message arguments                           |
| code      | string                 | Error code                                  |
| message   | string                 | Error message                               |
| target    | string                 | The target parameter that caused the error. |

## Delete a UNIX user configuration for an SVM

DELETE /name-services/unix-users/{svm.uuid}/{name}

**Introduced In:** 9.9

Deletes a UNIX user configuration for the specified SVM.

### Related ONTAP commands

- vserver services name-service unix-user delete

## Parameters

| Name     | Type   | In   | Required | Description                                   |
|----------|--------|------|----------|---|
| name     | string | path | True     | UNIX user name                                |
| svm.uuid | string | path | True     | UUID of the SVM to which this object belongs. |

## Response

```
Status: 200, Ok
```

## Error

```
Status: Default, Error
```

| Name  | Type                           | Description |
|-------|--------------------------------|-------------|
| error | <a href="#">returned_error</a> |             |

## Example error

```
{
  "error": {
    "arguments": {
      "code": "string",
      "message": "string"
    },
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

## Definitions

## See Definitions

error\_arguments

| Name    | Type   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

returned\_error

| Name      | Type                   | Description                                 |
|-----------|------------------------|---|
| arguments | array[error_arguments] | Message arguments                           |
| code      | string                 | Error code                                  |
| message   | string                 | Error message                               |
| target    | string                 | The target parameter that caused the error. |

# Retrieve UNIX user information for a user and SVM

GET /name-services/unix-users/{svm.uuid}/{name}

**Introduced In:** 9.9

Retrieves UNIX user information for the specified user and SVM.

## Related ONTAP commands

- vserver services name-service unix-user show

## Parameters

| Name     | Type          | In    | Required | Description                                   |
|----------|---------------|-------|----------|---|
| name     | string        | path  | True     | UNIX user name                                |
| svm.uuid | string        | path  | True     | UUID of the SVM to which this object belongs. |
| fields   | array[string] | query | False    | Specify the fields to return.                 |

## Response

Status: 200, Ok

| Name                 | Type                   | Description   |
|----------------------|------------------------|---|
| _links               | <a href="#">_links</a> |   |
| full_name            | string                 | User's full name.   |
| id                   | integer                | UNIX user ID of the specified user.   |
| name                 | string                 | UNIX user name to be added to the local database.                                     |
| primary_gid          | integer                | Primary group ID to which the user belongs.   |
| skip_name_validation | boolean                | Indicates whether or not the validation for the specified UNIX user name is disabled. |
| svm                  | <a href="#">svm</a>    | SVM, applies only to SVM-scoped objects.  |

## Example response

```
{  
  "_links": {  
    "self": {  
      "href": "/api/resourcelink"  
    }  
  },  
  "full_name": "Full User Name for user1",  
  "name": "user1",  
  "svm": {  
    "_links": {  
      "self": {  
        "href": "/api/resourcelink"  
      }  
    },  
    "name": "svml",  
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"  
  }  
}
```

## Error

Status: Default, Error

| Name  | Type           | Description |
|-------|----------------|-------------|
| error | returned_error |             |

## Example error

```
{  
  "error": {  
    "arguments": {  
      "code": "string",  
      "message": "string"  
    },  
    "code": "4",  
    "message": "entry doesn't exist",  
    "target": "uuid"  
  }  
}
```

## Definitions

## See Definitions

href

| Name | Type   | Description |
|------|--------|-------------|
| href | string |             |

\_links

| Name | Type | Description |
|------|------|-------------|
| self | href |             |

svm

SVM, applies only to SVM-scoped objects.

| Name   | Type   | Description   |
|--------|--------|---|
| _links | _links |   |
| name   | string | The name of the SVM. This field cannot be specified in a PATCH method.              |
| uuid   | string | The unique identifier of the SVM. This field cannot be specified in a PATCH method. |

error\_arguments

| Name    | Type   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

returned\_error

| Name      | Type                   | Description                                 |
|-----------|------------------------|---|
| arguments | array[error_arguments] | Message arguments                           |
| code      | string                 | Error code                                  |
| message   | string                 | Error message                               |
| target    | string                 | The target parameter that caused the error. |

# Update UNIX user information for a user and SVM

PATCH /name-services/unix-users/{svm.uuid}/{name}

**Introduced In:** 9.9

Updates UNIX user information for the specified user and SVM.

## Parameters

| Name     | Type   | In   | Required | Description                                   |
|----------|--------|------|----------|---|
| name     | string | path | True     | UNIX user name                                |
| svm.uuid | string | path | True     | UUID of the SVM to which this object belongs. |

## Request Body

| Name                 | Type                   | Description   |
|----------------------|------------------------|---|
| _links               | <a href="#">_links</a> |   |
| full_name            | string                 | User's full name.   |
| id                   | integer                | UNIX user ID of the specified user.   |
| name                 | string                 | UNIX user name to be added to the local database.                                     |
| primary_gid          | integer                | Primary group ID to which the user belongs.   |
| skip_name_validation | boolean                | Indicates whether or not the validation for the specified UNIX user name is disabled. |
| svm                  | <a href="#">svm</a>    | SVM, applies only to SVM-scoped objects.  |

## Example request

```
{  
    "_links": {  
        "self": {  
            "href": "/api/resourcelink"  
        }  
    },  
    "full_name": "Full User Name for user1",  
    "name": "user1",  
    "svm": {  
        "_links": {  
            "self": {  
                "href": "/api/resourcelink"  
            }  
        },  
        "name": "svml",  
        "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"  
    }  
}
```

## Response

```
Status: 200, Ok
```

## Error

```
Status: Default
```

## ONTAP Error Response Codes

| Error Code | Description   |
|------------|---|
| 23724128   | The specified Unix user full-name contains invalid character ':'  |
| 23724089   | The specified UNIX user full-name is too long. Maximum supported length is 256 characters.                                  |
| 23724055   | Internal error. Failed to modify the UNIX user for the SVM. Verify that the cluster is healthy, then try the command again. |
| 23724090   | Configuring individual entries is not supported because file-only configuration is enabled.                                 |

| Name  | Type           | Description |
|-------|----------------|-------------|
| error | returned_error |             |

## Example error

```
{  
  "error": {  
    "arguments": {  
      "code": "string",  
      "message": "string"  
    },  
    "code": "4",  
    "message": "entry doesn't exist",  
    "target": "uuid"  
  }  
}
```

## Definitions

## See Definitions

href

| Name | Type   | Description |
|------|--------|-------------|
| href | string |             |

\_links

| Name | Type | Description |
|------|------|-------------|
| self | href |             |

svm

SVM, applies only to SVM-scoped objects.

| Name   | Type   | Description   |
|--------|--------|---|
| _links | _links |   |
| name   | string | The name of the SVM. This field cannot be specified in a PATCH method.              |
| uuid   | string | The unique identifier of the SVM. This field cannot be specified in a PATCH method. |

unix\_user

| Name                 | Type    | Description   |
|----------------------|---------|---|
| _links               | _links  |   |
| full_name            | string  | User's full name.   |
| id                   | integer | UNIX user ID of the specified user.   |
| name                 | string  | UNIX user name to be added to the local database.                                     |
| primary_gid          | integer | Primary group ID to which the user belongs.   |
| skip_name_validation | boolean | Indicates whether or not the validation for the specified UNIX user name is disabled. |

| Name | Type | Description                              |
|------|------|--|
| svm  | svm  | SVM, applies only to SVM-scoped objects. |

#### error\_arguments

| Name    | Type   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

#### returned\_error

| Name      | Type                   | Description                                 |
|-----------|------------------------|---|
| arguments | array[error_arguments] | Message arguments                           |
| code      | string                 | Error code                                  |
| message   | string                 | Error message                               |
| target    | string                 | The target parameter that caused the error. |

## **Copyright information**

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—with prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

## **Trademark information**

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.