



Install the NetApp supported plug-ins

SnapCenter software

NetApp
February 20, 2026

This PDF was generated from https://docs.netapp.com/us-en/snapcenter/protect-nsp/add_hosts_and_install_plug_in_packages_on_remote_hosts.html on February 20, 2026. Always check docs.netapp.com for the latest.

Table of Contents

- Install the NetApp supported plug-ins 1
 - Add hosts and install plug-in packages on remote hosts 1
 - Install SnapCenter Plug-in Packages for Linux, Windows, or AIX on multiple remote hosts by using cmdlets 4
 - Install the NetApp supported plug-ins on Linux hosts by using the command-line interface 5
 - Monitor the status of installing NetApp supported plug-ins 6

Install the NetApp supported plug-ins

Add hosts and install plug-in packages on remote hosts

You must use the SnapCenter Add Host page to add hosts, and then install the plug-in packages. The plug-ins are automatically installed on the remote hosts. You can add a host and install the plug-in packages either for an individual host or for a cluster.

Before you begin

- You should be a user that is assigned to a role that has the plug-in install and uninstall permissions, such as the SnapCenter Admin role.
- You should ensure that the message queueing service is running.
- If you are using group Managed Service Account (gMSA), you should configure gMSA with administrative privileges.

[Configure group Managed Service Account on Windows Server 2016 or later for custom applications](#)



- For Windows host, you must ensure that you select SnapCenter Plug-in for Windows.


About this task

- You cannot add a SnapCenter Server as a plug-in host to another SnapCenter Server.
- If you install plug-ins on a cluster (WSFC), the plug-ins are installed on all of the nodes of the cluster.

Steps

1. In the left navigation pane, select **Hosts**.
2. Verify that the **Managed Hosts** tab is selected at the top.
3. Select **Add**.
4. In the Hosts page, perform the following actions:

For this field...	Do this...
Host Type	<p>Select the host type:</p> <ul style="list-style-type: none">• Windows• Linux• AIX <p> The NetApp supported plug-ins can be used in Windows, Linux, and AIX environments.</p> <p> Storage and Oracle applications are supported on AIX.</p>




For this field...	Do this...
Host name	<p>Enter the fully qualified domain name (FQDN) or the IP address of the host.</p> <p>SnapCenter depends on the proper configuration of the DNS. Therefore, the best practice is to enter the FQDN.</p> <p>For Windows environments, the IP address is supported for untrusted domain hosts only if it resolves to the FQDN.</p> <p>You can enter the IP addresses or FQDN of a stand-alone host.</p> <p>If you are adding a host by using SnapCenter and the host is part of a subdomain, you must provide the FQDN.</p>
Credentials	<p>Either select the credential name that you created, or create new credentials.</p> <p>The credentials must have administrative rights on the remote host. For details, see the information about creating credentials.</p> <p>You can view details about the credentials by positioning your cursor over the credential name that you specified.</p> <div data-bbox="873 1182 927 1234" style="display: inline-block; vertical-align: middle;">  </div> <div data-bbox="987 1161 1442 1262" style="display: inline-block; vertical-align: middle; border-left: 1px solid #ccc; padding-left: 10px; margin-left: 10px;"> <p>The credentials authentication mode is determined by the host type that you specify in the Add Host wizard.</p> </div>

5. In the **Select Plug-ins to Install** section, select the plug-ins to install.

You can install the following plug-ins from the list:

- MongoDB
- ORASCPM (displayed as Oracle Applications)
- SAP ASE
- SAP MaxDB
- Storage

6. (Optional) Select **More Options** to install the other plug-ins.

For this field...	Do this...
Port	<p>Either retain the default port number, or specify the port number.</p> <p>The default port number is 8145. If the SnapCenter Server was installed on a custom port, that port number will be displayed as the default port.</p> <div style="border-left: 1px solid #ccc; padding-left: 10px; margin-top: 10px;">  <p>If you manually installed the plug-ins and specified a custom port, you must specify the same port. Otherwise, the operation fails.</p> </div>
Installation Path	<p>The NetApp supported plug-ins can be installed on either a Windows system or Linux system.</p> <ul style="list-style-type: none"> • For the SnapCenter Plug-ins Package for Windows, the default path is C:\Program Files\NetApp\SnapCenter. <p>Optionally, you can customize the path.</p> <ul style="list-style-type: none"> • For SnapCenter Plug-ins Package for Linux and SnapCenter Plug-ins Package for AIX, the default path is /opt/NetApp/snapcenter. <p>Optionally, you can customize the path.</p>
Skip preinstall checks	<p>Select this check box if you already installed the plug-ins manually and you do not want to validate whether the host meets the requirements for installing the plug-in.</p>
Use group Managed Service Account (gMSA) to run the plug-in services	<p>For Windows host, select this check box if you want to use group Managed Service Account (gMSA) to run the plug-in services.</p> <div style="border-left: 1px solid #ccc; padding-left: 10px; margin-top: 10px;">  <p>Provide the gMSA name in the following format: domainName\accountName\$.</p> </div> <div style="border-left: 1px solid #ccc; padding-left: 10px; margin-top: 10px;">  <p>gMSA will be used as a log on service account only for SnapCenter Plug-in for Windows service.</p> </div>

7. Select **Submit**.

If you have not selected the **Skip prechecks** checkbox, the host is validated to verify whether the host meets the requirements for installing the plug-in. The disk space, RAM, PowerShell version, .NET version,

location (for Windows plug-ins), and Java version (for Linux plug-ins) are validated against the minimum requirements. If the minimum requirements are not met, appropriate error or warning messages are displayed.

If the error is related to disk space or RAM, you can update the `web.config` file located at `C:\Program Files\NetApp\SnapCenter\WebApp` to modify the default values. If the error is related to other parameters, you must fix the issue.



In an HA setup, if you are updating `SnapManager.Web.UI.dll.config`, you must update the file on both nodes and restart the SnapCenter App Pool.

Windows default path is `C:\Program Files\NetApp\SnapCenter\WebApp\SnapManager.Web.UI.dll.config`

Linux default path is

`/opt/NetApp/snapcenter/SnapManagerWeb/SnapManager.Web.UI.dll.config`

8. If host type is Linux, verify the fingerprint, and then select **Confirm and Submit**.



Fingerprint verification is mandatory even if the same host was added earlier to SnapCenter and the fingerprint was confirmed.

9. Monitor the installation progress.

The installation-specific log files are located at `/custom_location/snapcenter/logs`.

Install SnapCenter Plug-in Packages for Linux, Windows, or AIX on multiple remote hosts by using cmdlets

You can install the SnapCenter Plug-in Packages for Linux, Windows, or AIX on multiple hosts simultaneously by using the `Install-SmHostPackage` PowerShell cmdlet.

Before you begin

The user adding a host should have the administrative rights on the host.



Storage and Oracle applications are supported on AIX.

Steps

1. Launch PowerShell.
2. On the SnapCenter Server host, establish a session using the `Open-SmConnection` cmdlet, and then enter your credentials.
3. Install the plug-in on multiple hosts using the `Install-SmHostPackage` cmdlet and the required parameters.

The information regarding the parameters that can be used with the cmdlet and their descriptions can be obtained by running `Get-Help command_name`. Alternatively, you can also refer to the [SnapCenter Software Cmdlet Reference Guide](#).

You can use the `-skipprecheck` option when you have installed the plug-ins manually and do not want to validate whether the host meets the requirements to install the plug-in.

4. Enter your credentials for remote installation.

Install the NetApp supported plug-ins on Linux hosts by using the command-line interface

You should install the NetApp supported plug-ins by using the SnapCenter user interface (UI). If your environment does not allow remote installation of the plug-in from the SnapCenter UI, you can install the NetApp supported plug-ins either in console mode or in silent mode by using the command-line interface (CLI).

Steps

1. Copy the SnapCenter Plug-ins Package for Linux installation file (snapcenter_linux_host_plugin.bin) from C:\ProgramData\NetApp\SnapCenter\Package Repository to the host where you want to install the NetApp supported plug-ins.

You can access this path from the host where the SnapCenter Server is installed.

2. From the command prompt, navigate to the directory where you copied the installation file.
3. Install the plug-in: `path_to_installation_bin_file/snapcenter_linux_host_plugin.bin -i silent -DPORT=port_number_for_host -DSERVER_IP=server_name_or_ip_address -DSERVER_HTTPS_PORT=port_number_for_server`
 - -DPORT specifies the SMCORE HTTPS communication port.
 - -DSERVER_IP specifies the SnapCenter Server IP address.
 - -DSERVER_HTTPS_PORT specifies the SnapCenter Server HTTPS port.
 - -DUSER_INSTALL_DIR specifies the directory where you want to install the SnapCenter Plug-ins Package for Linux.
 - _DINSTALL_LOG_NAME specifies the name of the log file.

```
/tmp/sc-plugin-installer/snapcenter_linux_host_plugin.bin -i silent
-DPORT=8145 -DSERVER_IP=scserver.domain.com -DSERVER_HTTPS_PORT=8146
-DUSER_INSTALL_DIR=/opt
-DINSTALL_LOG_NAME=SnapCenter_Linux_Host_Plugin_Install_2.log
-DCHOSEN_FEATURE_LIST=CUSTOM
```

4. Add the host to the SnapCenter Server using the Add-Smhost cmdlet and the required parameters.

The information regarding the parameters that can be used with the command and their descriptions can be obtained by running *Get-Help command_name*. Alternatively, you can also refer to the [SnapCenter Software Cmdlet Reference Guide](#).

5. Log in to SnapCenter and upload the NetApp supported plug-in from the UI or by using PowerShell cmdlets.

You can upload the NetApp supported plug-in from the UI by referring to [Add hosts and install plug-in packages on remote hosts](#) section.

The SnapCenter cmdlet help and the cmdlet reference information contain more information about

PowerShell cmdlets.






[SnapCenter Software Cmdlet Reference Guide.](#)

Monitor the status of installing NetApp supported plug-ins

You can monitor the progress of SnapCenter plug-in package installation by using the Jobs page. You might want to check the progress of installation to determine when it is complete or if there is an issue.

About this task

The following icons appear on the Jobs page and indicate the state of the operation:

-  In progress
-  Completed successfully
-  Failed
-  Completed with warnings or could not start due to warnings
-  Queued

Steps

1. In the left navigation pane, click **Monitor**.
2. In the **Monitor** page, click **Jobs**.
3. In the **Jobs** page, to filter the list so that only plug-in installation operations are listed, do the following:
 - a. Click **Filter**.
 - b. Optional: Specify the start and end date.
 - c. From the Type drop-down menu, select **Plug-in installation**.
 - d. From the Status drop-down menu, select the installation status.
 - e. Click **Apply**.
4. Select the installation job and click **Details** to view the job details.
5. In the **Job Details** page, click **View logs**.

Copyright information

Copyright © 2026 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.